-----

## Format

CALL JOYMOTION(key-unit,x-return,y-return,
#sprite,row-index,column-index)

CALL JOYMOTION(key-unit,x-return,y-return,
#sprite,row-index,column-index,
key-return-variable)

CALL JOYMOTION(key-unit,x-return,y-return,
#sprite,row-index,column-index,
key-return-variable)
GOTO line-number

## Description

JOYMOTION combines commands JOYST, KEY, MOTION and a built in IF fire-button GOTO line-number. Keyboard key or fire button is in key-return-variable, but only joystick fire or key Q is used for GOTO line-number. As seen above line number option can be left out or furter key-return-variable can be left out too. Index is number of dots for row and column.

## **Programs**

>100 CALL CLEAR
>110 CALL CHAR(143,"FFFFFFFFFFFFFFFFFFFFFFFFFFFFFFFFFFFF
>120 CALL SPRITE(#1,143,2,9,19 0,20,0)
>130 CALL JOYMOTION(1,X,Y,#1,9
,9,K) GOTO 160   >140 PRINT X;Y;K   >150 GOTO 130   >160 PRINT X;Y;K;"FIRE"   170 GOTO 130

## Options:

See JOYMOTION or ONKEY or KEY for more XB changes created by RXB to speed up the programs and make them easier to read and write.